
EnviroGen Documentation

Release 3.0.1

Russell Garwood, Alan R.T. Spencer, Mark Sutton

Feb 10, 2024

CONTENTS

1	Relevant references	3
1.1	Software references:	3
1.2	Other references:	3
2	Table of Contents	5
2.1	Introduction	5
2.1.1	Overview	5
2.1.2	Variables	5
2.1.3	Quick start	5
2.2	EnviroGen options	6
2.2.1	Out	6
2.2.2	Dyn 1	8
2.2.3	Dyn 2	10
2.2.4	Noise	12
2.2.5	Combine	12
2.2.6	Col	17
2.2.7	Stack	18

The [Enviro]ment [Gen]erator program.

EnviroGen is a utility package to create highly customised image stacks which can loaded as the environment for REvoSim runs. The package allows image stacks to be created using a number of different algorithms, and thus individual variables (e.g. rate of change, complexity) to be isolated and their impact on simulations studied. It also contains several convenience functions: for example, it allows noise image stacks to be created, two image stacks to be combined, uniform coloured stacks to be created, and a stack to be created from a single image.



t:@palaeoware

e:palaeoware@gmail.com

w:<https://github.com/palaeoware>

RELEVANT REFERENCES

1.1 Software references:

Garwood, R.J., Spencer A.R.T. and Sutton, M.D., 2019. REvoSim: Organism-level simulation of macro- and microevolution. *Palaeontology* 62(3),339-355. <https://doi.org/10.1111/pala.12420>

Furness, E.N., Garwood, R.J. & Sutton, M.D. 2023. REvoSim v3: A fast evolutionary simulation tool with ecological processes. *Journal of Open Source Software* 8(89): 5284. doi: *10.21105/joss.05284* <*10.21105/joss.05284*>

1.2 Other references:

Furness, E.N., Garwood, R.J., Mannion, P.D. and Sutton, M.D., 2021. Evolutionary simulations clarify and reconcile biodiversity-disturbance models. *Proceedings of the Royal Society B*, 288(1949), p.20210240. <https://doi.org/10.1098/rspb.2021.0240>

Furness, E.N., Garwood, R.J., Mannion, P. D. & Sutton, M.D. 2021. Productivity, niche availability, species richness and extinction risk: Untangling relationships using individual-based simulations. *Ecology and Evolution* 11(13): 8923-8940. <https://doi.org/10.1002/ece3.7730>

TABLE OF CONTENTS

2.1 Introduction

2.1.1 Overview

EnviroGen is a utility program for REvoSim: an individual-based evolutionary model, using a simplified first-principles evolutionary model to simulate large populations incorporating space, over geological time. An integral part of REvoSim is its fitness algorithm, which is linked to an environment within the software, which is in the form of an RGB raster image. REvoSim is designed for versatility, and many simulations will require a changing environment throughout the course of a run. These dynamic environments are loaded in the form of image stacks. EnviroGen provides two different mechanisms for generating these dynamic environments, with a large number of options allowing the environments to be tailored to specific questions. For example, environments can have a high degree of fragmentation of colours to study endemism, be primarily defined by gradients, or have a range of complexities. There are numerous convenience functions built in to the software to ease processing image stacks.

2.1.2 Variables

Each mode of environmental generation has its own tab in the Environmental Setting dock, which by default is shown on the right of the main window.

This has a number of tabs on the top: Dyn 1 and Dyn 2 are EnviroGen's dynamic environments, noise allows the user to create a stack of noise images, Comb allows stacks to be combined, Col allows the creation of solid colour stacks, and Stack allows the creation of a stack from a single image. The first tab, out, has output settings.

2.1.3 Quick start

An image stack can be generated by hitting run on the top toolbar. This is stored by default on the desktop for all operating systems: images are placed within a folder titled *EnviroGen_output*, and are saved as .pngs to as a compromise between file size and lossless compression.

The toolbar has the following options:

Run


Generate environmental images.

Run batch

Create multiple replicates of environmental images in parallel.

Stop

Stop generating images.



Pause

Temporarily stop generating images.

About

Launch dialogue with information about EnviroGen.

2.2 EnviroGen options

Within the Settings dock of EnviroGen are a number of different modes of creating / modifying environments. All can be accessed by changing the chosen tab at the top of this dock. The tabs are introduced below.

2.2.1 Out

This tab has EnviroGen output options.

Save images


When checked images are saved as .pngs into a folder called *EnviroGen_output* in the output folder. If the folder and files it contains already exists, EnviroGen overwrites any older files with file name conflicts.

Save location

This defines the location in which the above folder is created - it is, by default, the desktop in all operating systems.

Change

Launches a file dialogue to change the save location.



The screenshot shows the 'Out' tab of the EnviroGen interface. At the top, there are seven tabs: 'Out', 'Dyn 1', 'Dyn 2', 'Noise', 'Comb', 'Col', and 'Stack'. The 'Out' tab is selected. Below the tabs, there is a text block that reads: 'Select output options here. You can define the type of environment you would like to generate either using the selection box below, or by choosing one of the tabs to the right, in which you can find the settings for each environment type. Press play to start generating.'

Output:

- ☒ Save images
- Save Location:
C:/Users/artsp/Desktop
Change...
- Generate for:
500
- Image size:
100
- Environment type:
Dynamic Two

Display:

- ☒ Resize image

Generate for

Defines the number number of environmental images created.

Image size

This dictates the size of the image files created.

Environment type

The type of environment generated is defined using this dropdown menu. When changing to any other tab, the selected environment change is changed here to reflect the current tab, and thus when Run is selected on any other tab, that environment type is generated.

Resize image

If selected this resizes the image to fill the GUI (but does not alter the size of the image that is created, as defined in image size).

2.2.2 Dyn 1

EnviroGen provides two primary models for the creation of dynamic environment. The first employs a user-defined number of seeds of varying colours and sizes, which drift across the environmental image. A Laplacian smooth is used to define the colour between these seed points.

The following options are provided to control the environment:

Number

This is the number of seeds which are used to create the environment.

Max size

This defines the maximum size these seeds can achieve, in pixels.

Max size velocity

By default the size of the seeds changes over the course of a run. This option dictates the maximum change in size any given iteration in pixels. Setting it to zero will stop the seeds changing in size (by they will still initialise at different sizes).

Max velocity

This defines the maximum velocity of the seeds in terms of their movement across the grid in pixels/iteration. Note that these are soft limits - the seeds can exceed these, but will generally move towards the maximum in any direction if it is above this figure.

Overlap blur factor

When two seeds overlap, this option defines the amount of blurring in the overlapping region. A setting of one ensures that overlapping pixels smooth. Larger than this creates a square zone of blurring around the overlapped sections: at very large values this could create changes to the whole environment when seeds overlap.

Toroidal

When this option is checked, the environment wraps around to avoid boundary effects. Seeds that disappear from one side will appear from the other - the same is true of top and bottom.

Convergence

This defines the extent to which the Laplacian smooth creates gradients between seeds - the smaller the number, the smoother the gradients (but the longer the smooth takes to converge, especially for the first environmental image).

Speed factor

This is a convenience option allowing the simulation to be changed only in speed: not any other factor. This option is a multiplier for all velocities.

Out Dyn 1 Dyn 2 Noise Comb Col Stack

Please enter the settings for the dynamic environment below. Most are obvious. Convergence sets the amount of smoothing between spots and background. 0.01 is very smooth, but will initially take about a minute to create environment.

Seeds:

Number	4
Max size	14
Max size velocity	5
Max velocity	0.10
Max colour velocity	5
Overlap blur factor	1

Background:

☒ Toroidal


Convergence	0.1000
Speed factor	1.000

☐ Universal Blur

Universal blur

By default the Laplacian smooth only creates gradients *between* the seeds. When this option is selected the seeds define pixel colours, but then the smoothing smooths over these, as well as the space between seeds.

An example environment created with dynamic environment one is shown below.



2.2.3 Dyn 2

The second model for generation of dynamic environments is also based on moving seeds, but differs in being additive, and lacking smoothing. Seeds, or objects, have a sizes, colours and velocities, and changes (“accelerations”) are applied to these. Limits can be placed on values, their first derivative (e.g. velocity), or their second derivative (e.g. acceleration). Dynamic environment two tends to have higher gradients between pixels than the first, and using the default settings it changes more rapidly. It is quicker generating environments than dynamic environment one. Options are as follows:

Object count

This is the number of seeds which are used to create the environment.

Maximum object size

The maximum possible object size. In this dynamic environment all limits are hard, and thus cannot be exceeded.

Out Dyn 1 Dyn 2 Noise Comb Col Stack

Please enter the settings for the dynamic environment below. Most are obvious.

Object Count	15
Maximum Object Size	100
Minimum Object Size	10
Maximum Tightness	8.00
Minimum Tightness	0.10
Maximum Velocity	3.00
Maximum Size Velocity	3.00
Maximum Colour Velocity	8.00
Maximum Tightness Velocity	0.40
Maximum Acceleration	1.00
Max Size Acceleration	2.00
Max Tightness Acceleration	0.10
Max Colour Acceleration	2.00
Speed Factor	1.00
Apply accelerations every ...	1

Minimum object size

This is the minimum size.

Maximum tightness

Tightness controls the rate at which the colour-influence of each seed drops off away from its centre. High tightness values produce a rapid drop-off - i.e. the colour influence is more tightly concentrated near its centre. Maximum tightness is the highest value this can reach.

Minimum tightness

The minimum tightness value (see above).

Maximum ... velocity

There then follow options to provide a hard limits to the velocity of the objects, and also a maximum to the rate of change of their colour, size and tightness.

Maximum ... acceleration

The next four options allow limits to be placed on the rate of change of the rate of change of velocity, size, tightness and colour.

Speed factor

As with dynamic environment one, there is a multiplier allowing environmental settings to be repeated with the only difference being rate of change (i.e. all are multiplied by this factor).

Apply accelerations every...

Within this dynamic environment accelerations do not need to be applied every iteration. Rather than can be applied.

An example environment created with dynamic environment two is shown below.

2.2.4 Noise

To study some phenomena a level of noise on an environment may be desirable. This tab creates a noise image using 10Mb of quantum-generated random numbers from randomnumbers.info that are packaged into the executable. These are loaded on program launch from a starting point based on a pseudorandom number, seeded on the time at launch. These can then be combined with any other environment as required using the comb tab. It creates random R,G, and B values for every pixel within the limits desired, and offers two options:

Minimum value

This is the minimum value for the noise (i.e. the minimum value any R, G or B value can take).

Maximum value

The maximum value.

An example noise environment is shown below.

2.2.5 Combine


This allows image stacks to be combined or concatenated, and thus allows the construction of increasingly complex environments. It takes two input stacks, and allows the influence of each while they are being combined to be defined. RGB values for both stacks are added. If they are limited to a maximum of 255, and an 8 bit image is output. Options are as follows:


Stack one


This is the first image stack. The change button opens a file dialogue and allows a folder to be selected, the location of which appears here.

Stack two

As above, but the second image stack.







Out

Dyn 1

Dyn 2

Noise

Comb

Col

Stack

Combines two stacks between the start and end of either stack. If start slice is greater than zero, it will copy stack one to start slice, and then combine stack two from that point on. Percentage start and end dictate influence of stack one for slices which are combined, and the programme interpolates between these. If stack one ends, stack two will be copied to the end. This can also be used to concatenate stacks by setting start to the size of stack one.

Stack one:

Change...

Stack two:

Change...

Start slice:

0

Percent influence stack one (start combine):

50

Percent influence stack one (end combine):

50

Start slice


EnviroGen combines image stacks from this slice (note it employs C++ numbering, so zero is the first slice, etc.). Before this point, if this is not zero, it will merely copy stack one. If stack one ends before the last image in stack two, it will copy stack two to the end. Stacks can be concatenated by setting the starty slice to the size of stack one.

Percent influence

Percentage start and end dictate influence of stack one for slices which are combined; the programme interpolates between these percentages, allowing smooth or abrupt changes in the combined region as required.

Note that if “generate for” in the output tab is set to be higher than the number of images tab one, or start slice plus tab two, EnviroGen will generate black environmental images for the remainder of the run.


2.2.6 Col



This is a convenience function to create an image stack comprising a single colour (which can they be combined with

other images if desired). The colour can be set either by entering red blue and green levels into the spin boxes on this tab, or using the colour picker.

2.2.7 Stack



This tab allows a stack to be created from a single image. Choose image launches a file dialogue, and once an image has been chosen, it is converted to a stack and placed in the output folder.